

Firmware Upgrade for 25R-C Step by Step

Version: 20180317

Note: Please close all the anti-virus software before download package.

Download the firmware upgrade package from:

a) <https://www.glotrends-store.com/downloads/>

b) https://drive.google.com/open?id=1h1ako0GOMGqcUc7Mn_yF8yr-5C-7uQfb

- 1) USB Cable connect with PC
25R-C power on

Note: No need to load the hard drive during firmware upgrade.




- 2) Unzip the file;
See 3 files




- 170505_B5_27_82.bin
- as_mp_Tool v0.5.ini
- ASM105xMPTool.exe

- 3) Right click the ASM105xMPTool.exe
Run the exe with administrator



- 4) As below picture, Step 1: click and input the password “asmedia”;
Step 2: after input password, 25R-C information will appear automatically;
Step 3: Select the idle time
Step 4: Click and open the file “170505_B5_27_82.bin”;
Step 5: Click and run the bin file;



- 5) Step 6: "PASS" will appear if successfully;
- Step 7: Exit the exe;
- Step 8: Restart the 25R-C

