

Firmware Upgrade for 35R-C Step by Step

Version: 20180317

Note: Please close all the anti-virus software before download package.

Download the firmware upgrade package from:


- a) <https://www.glotrends-store.com/downloads/>
- b) https://drive.google.com/open?id=13pgRf5mCn5FZUzKfc_xs5q_kBNI7qN9m

- 1) USB Cable connect with PC
35R-C power on

Note: No need to load the hard drive during firmware upgrade.



- 2) Unzip the file;
See 3 files




- 170505_B5_27_82.bin
- as_mp_Tool v0.5.ini
- ASM105xMPTool.exe

- 3) Right click the ASM105xMPTool.exe
Run the exe with administrator



- 4) As below picture, Step 1: click and input the password “asmedia”;
Step 2: after input password, 35R-C information will appear automatically;
Step 3: Select the idle time
Step 4: Click and open the file “170505_B5_27_82.bin”;
Step 5: Click and run the bin file;



- 5) Step 6: "PASS" will appear if successfully;
- Step 7: Exit the exe;
- Step 8: Restart the 35R-C

